User Guide

Weather Monitoring System

Server

Setting up

Edit the *server.conf* file with the required settings.

@server_com	Port for socket communication
	Default: 6666
@rmi_port	Port for the RMI Registry
	Default: 1099

Running the Server

- 1. Start rmiregistry
- 2. Start the server using the **Server.jar** executable jar file.

Managing users

Add New User

Command format: @add <username> <password>

Example: @add user123 pass123

Remove Existing User

Command format: @remove <username>

Example: @remove user123

Note:

- 1. AES Encryption is used to secure your usernames and passwords. User details are stored in **users.conf** file.
- 2. Server needs to be restarted once a change is made to its configurations
- 3. If a user is removed while he is connected, automatically his session gets destroyed.

Shutting down the Server

1. Type 'exit' and press Enter.

```
Loading configurations...

Socket communication port: 9999

RMI port: 1099

Server started...

Listening on port 9999 for sensors

Type 'exit' to shutdown server

exit

Shutting down server...
```

Figure 1: A healthy run

Sensor

Setting up

Edit the *sensor.conf* file with the required settings.

@sensor_com	Port for socket communication
	Default: 6666
@server	Server's IP address
	Default: localhost

Running the Sensor

1. Start the sensor application using the **Sensor.jar** executable jar file.

Shutting down the Sensor

2. Type 'exit' and press Enter.

```
Loading configurations...

Server: localhost:6666

Enter location: Kandy

Available Sensor Types:

1. Air Pressure

2. Humidity

3. Rainfall

4. Temperature

Select type of sensor: 3

Connected to server

Type 'exit' to stop the sensor exit

Sensor shutting down...
```

Figure 2: A healthy run

Monitoring Station Dashboard

Setting up

Edit the *station.conf* file with the required settings.

@rmi_host	Host address for RMI
	Default: localhost
@rmi_port	Port for RMI
	Default: 1099


Running the Station

- 1. Start the station application using the **Station.jar** executable jar file.
- 2. Login to the system



Default: Username: user Password: pass

3. Tool tips are available on the dashboard. Move your cursor on to elements to see what they do.



Shutting down the Station

1. Click on the 'Exit' button on the right top corner and confirm.